

Instructions to use SpeechAttentionGAN

Environment

PYTHONPATH="{PYTHONPATH}:/path/to/SpeechAttentionGAN"

pip install -r requirements.txt

Organize data

SpeechAttentionGAN
data_cache

clean	train
	test
noisy	train
	test

Train

```
python train.py --dataroot data_cache --name <model name> --model
attention_gan --dataset_mode audio --pool_size 50 --no_dropout --norm
instance --lambda_A 10 --lambda_B 10 --lambda_identity 0.5 --
load_size_h 128 --load_size_w 128 --crop_size 128 --preprocess resize --
batch_size 4 --niter 200 --niter_decay 0 --gpu_ids 0 --display_id 0 --
display_freq 100 --print_freq 100 --input_nc 1 --output_nc 1 --
use_cycled_discriminators --use_mask --max_mask_len 50
```

Test

```
python test.py --dataroot data_cache --name <model name> --model
attention_gan --dataset_mode audio --norm instance --phase test --
no_dropout --load_size_h 128 --load_size_w 128 --crop_size 128 --
batch_size 1 --gpu_ids 0 --input_nc 1 --output_nc 1 --use_mask
```

Note:

1. Use `--single_direction` flag during test if you do not have noisy test data and you only have clean audio.
2. Pre-trained checkpoints can be put in the AttentionGAN folder can be directly used for testing.
3. To use phase :

1. Use the `--use_phase` flag
2. Use `input_nc` and `output_nc` with option 2
4. `--use_mask` and `--use_cycled_discriminators` can be used or omitted as requires